



- ▶ Version 10.1
- ▶ Grid Improvements
- ▶ Row TreeVisibleDepth

Row TreeVisibleDepth Method

This method is used to set the maximum visible depth of data in rows of a Grid.

The argument to RowSetVisibleDepth is a numeric scalar as follows

[1] Depth: integer

All rows in the grid that have a value of **RowTreeDepth** less than or equal to Depth are expanded. Rows with a value of Row TreeDepth greater than Depth are collapsed.

Note: Expanding and Retracting events are not generated when this method is called.

```
'F'[]WC'Form' 'Grid: TreeView Feature'  
'F.G'[]WC'Grid'(30 2p2/130)  
F.G.RowTreeDepth+30p0 1 2 2
```

	A	B
⊕ 1	1	1
⊕ 5	5	5
⊕ 9	9	9
⊕ 13	13	13
⊕ 17	17	17
⊕ 21	21	21
⊕ 25	25	25
⊕ 29	29	29

Dyalog Ltd
 South Barn
 Minchens Court
 Minchens Lane
 Bramley
 Hampshire
 RG26 5BH
 United Kingdom

Phone:
 + 44 (0) 1256 830 030

Fax:
 + 44 (0) 1256 830 031

e-mail:
 sales@dyalog.com



- ▶ Version 10.1
- ▶ Grid Improvements
- ▶ Row TreeVisibleDepth

F.G.RowSetVisibleDepth 1

	A	B
☐ 1	1	1
└─ ☐ 2	2	2
☐ 5	5	5
└─ ☐ 6	6	6
☐ 9	9	9
└─ ☐ 10	10	10
☐ 13	13	13
└─ ☐ 14	14	14

F.G.RowSetVisibleDepth 99

	A	B
☐ 1	1	1
└─ ☐ 2	2	2
└─ 3	3	3
└─ 4	4	4
☐ 5	5	5
└─ ☐ 6	6	6
└─ 7	7	7
└─ 8	8	8

Dyalog Ltd

South Barn
Minchens Court
Minchens Lane
Bramley
Hampshire
RG26 5BH
United Kingdom

Phone:

+ 44 (0) 1256 830 030

Fax:

+ 44 (0) 1256 830 031

e-mail:

sales@dyalog.com